
User Manual

for S32K14X OCU Driver

Document Number: UM2OCUASR4.3 Rev0001R1.0.1
Rev. 1.0





Contents

Section number	Title	Page
Chapter 1		
Revision History		
Chapter 2		
Introduction		
2.1	Supported Derivatives.....	11
2.2	Overview.....	11
2.3	About this Manual.....	12
2.4	Acronyms and Definitions.....	12
2.5	Reference List.....	13
Chapter 3		
Driver		
3.1	Requirements.....	15
3.2	Driver Design Summary.....	15
3.3	Hardware resources.....	16
3.4	Deviation from Requirements.....	16
3.5	Driver limitations.....	17
3.6	Driver usage and configuration tips.....	18
3.7	Runtime Errors.....	18
3.8	Software specification.....	18
3.8.1	Define Reference.....	18
3.8.1.1	Define OCU_VENDOR_ID.....	18
3.8.1.2	Define OCU_AR_RELEASE_MAJOR_VERSION.....	18
3.8.1.3	Define OCU_AR_RELEASE_MINOR_VERSION.....	18
3.8.1.4	Define OCU_AR_RELEASE_REVISION_VERSION.....	19
3.8.1.5	Define OCU_SW_MAJOR_VERSION.....	19
3.8.1.6	Define OCU_SW_MINOR_VERSION.....	19
3.8.1.7	Define OCU_SW_PATCH_VERSION.....	19
3.8.1.8	Define OCU_DEINIT_ID.....	20

Section number	Title	Page
3.8.1.9	Define OCU_DISABLENOTIFICATION_ID.....	20
3.8.1.10	Define OCU_ENABLENOTIFICATION_ID.....	20
3.8.1.11	Define OCU_GETCOUNTER_ID.....	21
3.8.1.12	Define OCU_GETVERSIONINFO_ID.....	21
3.8.1.13	Define OCU_INIT_ID.....	21
3.8.1.14	Define OCU_PROCESSNOTIFICATION_ID.....	22
3.8.1.15	Define OCU_SETABSOLUTETHRESHOLD_ID.....	22
3.8.1.16	Define OCU_SETCLOCKMODE_ID.....	22
3.8.1.17	Define OCU_SETPINACTION_ID.....	23
3.8.1.18	Define OCU_SETPINSTATE_ID.....	23
3.8.1.19	Define OCU_SETRELATIVETHRESHOLD_ID.....	23
3.8.1.20	Define OCU_STARTCHANNEL_ID.....	24
3.8.1.21	Define OCU_STOPCHANNEL_ID.....	24
3.8.1.22	Define OCU_E_ALREADY_INITIALIZED.....	24
3.8.1.23	Define OCU_E_BUSY.....	25
3.8.1.24	Define OCU_E_INIT_FAILED.....	25
3.8.1.25	Define OCU_E_NO_VALID_NOTIF.....	26
3.8.1.26	Define OCU_E_PARAM_INSTANCE.....	26
3.8.1.27	Define OCU_E_PARAM_INVALID_ACTION.....	26
3.8.1.28	Define OCU_E_PARAM_INVALID_CHANNEL.....	27
3.8.1.29	Define OCU_E_PARAM_INVALID_STATE.....	27
3.8.1.30	Define OCU_E_PARAM_INVALID_VALUE.....	28
3.8.1.31	Define OCU_E_PARAM_NO_PIN.....	28
3.8.1.32	Define OCU_E_PARAM_POINTER.....	28
3.8.1.33	Define OCU_E_UNINIT.....	29
3.8.1.34	Define OCU_DEINIT_API.....	29
3.8.1.35	Define OCU_GET_COUNTER_API.....	29
3.8.1.36	Define OCU_SET_ABSOLUTE_THRESHOLD_API.....	30
3.8.1.37	Define OCU_SET_CLOCK_MODE_API.....	30

Section number	Title	Page
3.8.1.38	Define OCU_SET_PIN_ACTION_API.....	30
3.8.1.39	Define OCU_SET_PIN_STATE_API.....	30
3.8.1.40	Define OCU_SET_RELATIVE_THRESHOLD_API.....	31
3.8.1.41	Define OCU_VERSION_INFO_API.....	31
3.8.1.42	Define OCU_NOTIFICATION_SUPPORTED.....	31
3.8.1.43	Define OCU_DEV_ERROR_DETECT.....	31
3.8.2	Enum Reference.....	31
3.8.2.1	Enumeration Ocu_ChannelStatusType.....	32
3.8.2.2	Enumeration Ocu_CountDirectionType.....	32
3.8.2.3	Enumeration Ocu_GlobalStateType.....	32
3.8.2.4	Enumeration Ocu_PinActionType.....	33
3.8.2.5	Enumeration Ocu_PinStateType.....	33
3.8.2.6	Enumeration Ocu_ReturnType.....	34
3.8.2.7	Enumeration Ocu_SelectPrescalerType.....	34
3.8.3	Function Reference.....	35
3.8.3.1	Function Ocu_Init.....	35
3.8.3.2	Function Ocu_DeInit.....	35
3.8.3.3	Function Ocu_GetVersionInfo.....	36
3.8.3.4	Function Ocu_DisableNotification.....	37
3.8.3.5	Function Ocu_EnableNotification.....	37
3.8.3.6	Function Ocu_StartChannel.....	38
3.8.3.7	Function Ocu_StopChannel.....	39
3.8.3.8	Function Ocu_SetPinState.....	40
3.8.3.9	Function Ocu_SetPinAction.....	41
3.8.3.10	Function Ocu_GetCounter.....	42
3.8.3.11	Function Ocu_SetAbsoluteThreshold.....	43
3.8.3.12	Function Ocu_SetRelativeThreshold.....	44
3.8.3.13	Function Ocu_SetClockMode.....	45
3.8.4	Structs Reference.....	45

Section number	Title	Page
3.8.4.1	Structure Ocu_ConfigType.....	45
3.8.4.2	Structure Ocu_ChannelConfigType.....	46
3.8.4.3	Structure Ocu_IpConfigType.....	47
3.8.4.4	Structure Ocu_IpChannelConfigType.....	47
3.8.4.5	Structure Ocu_Ftm_IpConfigType.....	47
3.8.4.6	Structure Ocu_Ftm_ChannelConfigType.....	48
3.8.4.7	Structure Ocu_Ftm_ModuleConfigType.....	49
3.8.5	Types Reference.....	49
3.8.5.1	Typedef Ocu_ChannellpType.....	50
3.8.5.2	Typedef Ocu_ChannelType.....	50
3.8.5.3	Typedef Ocu_Ftm_ChannelType.....	50
3.8.5.4	Typedef Ocu_Ftm_ModuleType.....	50
3.8.5.5	Typedef Ocu_Ftm_ChannelControlType.....	50
3.8.5.6	Typedef Ocu_Ftm_ModuleControlType.....	50
3.8.5.7	Typedef Ocu_NotifyType.....	51
3.8.5.8	Typedef Ocu_ValueType.....	51
3.8.6	Variables Reference.....	51
3.9	Symbolic Names Disclaimer.....	51

Chapter 4 Tresos Configuration Plug-in

4.1	Configuration elements of Ocu.....	53
4.2	Form IMPLEMENTATION_CONFIG_VARIANT.....	53
4.3	Form OcuConfigurationOfOptionalApis.....	53
4.3.1	OcuDeInitApi (OcuConfigurationOfOptionalApis).....	54
4.3.2	OcuGetCounterApi (OcuConfigurationOfOptionalApis).....	54
4.3.3	OcuNotificationSupported (OcuConfigurationOfOptionalApis).....	54
4.3.4	OcuSetAbsoluteThresholdApi (OcuConfigurationOfOptionalApis).....	55
4.3.5	OcuSetPinActionApi (OcuConfigurationOfOptionalApis).....	55
4.3.6	OcuSetPinStateApi (OcuConfigurationOfOptionalApis).....	55

Section number	Title	Page
4.3.7	OcuSetRelativeThresholdApi (OcuConfigurationOfOptionalApis).....	56
4.3.8	OcuVersionInfoApi (OcuConfigurationOfOptionalApis).....	56
4.4	Form OcuGeneral.....	56
4.4.1	OcuDevErrorDetect (OcuGeneral).....	57
4.4.2	OcuEnableDualClockMode (OcuGeneral).....	57
4.4.3	OcuEnableUserModeSupport (OcuGeneral).....	57
4.4.4	Form OcuHwResourceConfig.....	58
4.4.4.1	OcuIsrHwId (OcuHwResourceConfig).....	58
4.4.4.2	OcuIsrEnable (OcuHwResourceConfig).....	59
4.4.4.3	OcuChannelIsUsed (OcuHwResourceConfig).....	59
4.5	Form OcuConfigSet.....	59
4.5.1	OcuCountdirection (OcuConfigSet).....	60
4.5.2	Form OcuChannel.....	60
4.5.2.1	OcuChannelId (OcuChannel).....	61
4.5.2.2	OcuAssignedHardwareChannel (OcuChannel).....	61
4.5.2.3	FtmHwChannel (OcuChannel).....	62
4.5.2.4	OcuDefaultThreshold (OcuChannel).....	62
4.5.2.5	OcuMaxCounterValue (OcuChannel).....	62
4.5.2.6	OcuNotification (OcuChannel).....	63
4.5.2.7	OcuOuptutPinUsed (OcuChannel).....	63
4.5.2.8	OcuOutputPinDefaultState (OcuChannel).....	63
4.5.2.9	OcuOutputPinAction (OcuChannel).....	64
4.5.2.10	OcuUseMcuReferencePoint (OcuChannel).....	64
4.5.2.11	OcuChannelTickDuration (OcuChannel).....	65
4.5.2.12	OcuMcuClockReferencePoint (OcuChannel).....	65
4.5.3	Form OcuHWSpecificSettings.....	66
4.5.3.1	OcuHardwareChannelId (OcuHWSpecificSettings).....	66
4.5.3.2	OcuFtmModule (OcuHWSpecificSettings).....	66
4.5.3.3	OcuClockSource (OcuHWSpecificSettings).....	67

Section number	Title	Page
4.5.3.4	OcuPrescale (OcuHWSpecificSettings).....	67
4.5.3.5	OcuPrescale_Alternate (OcuHWSpecificSettings).....	67
4.5.3.6	OcuPrescale_Alternate (OcuHWSpecificSettings).....	68
4.5.3.7	OcuDebugMode (OcuHWSpecificSettings).....	68
4.6	Form CommonPublishedInformation.....	69
4.6.1	ArReleaseMajorVersion (CommonPublishedInformation).....	69
4.6.2	ArReleaseMinorVersion (CommonPublishedInformation).....	70
4.6.3	ArReleaseRevisionVersion (CommonPublishedInformation).....	70
4.6.4	ModuleId (CommonPublishedInformation).....	71
4.6.5	SwMajorVersion (CommonPublishedInformation).....	71
4.6.6	SwMinorVersion (CommonPublishedInformation).....	72
4.6.7	SwPatchVersion (CommonPublishedInformation).....	72
4.6.8	VendorApiInfix (CommonPublishedInformation).....	73
4.6.9	VendorId (CommonPublishedInformation).....	73

Chapter 1

Revision History

Table 1-1. Revision History

Revision	Date	Author	Description
1.0	21/06/2019	NXP MCAL Team	Updated version for ASR 4.3.1S32K14XR1.0.1



Chapter 2

Introduction

This User Manual describes NXP Semiconductors AUTOSAR Output Compare Unit (Ocu) for S32K14X .

AUTOSAR Ocu driver configuration parameters and deviations from the specification are described in Ocu Driver chapter of this document. AUTOSAR Ocu driver requirements and APIs are described in the AUTOSAR Ocu driver software specification document.

2.1 Supported Derivatives

The software described in this document is intended to be used with the following microcontroller devices of NXP Semiconductors .

Table 2-1. S32K14X Derivatives

NXP Semiconductors	s32k148_lqfp144, s32k148_lqfp176, s32k148_mapbga100, s32k146_lqfp144, s32k146_lqfp100, s32k146_lqfp64, s32k146_mapbga100, s32k144_lqfp100, s32k144_lqfp64, s32k144_mapbga100, s32k142_lqfp100, s32k142_lqfp64, s32k118_lqfp48, s32k118_lqfp64, s32k142_lqfp48, s32k144_lqfp48, s32k148_lqfp100
--------------------	--

All of the above microcontroller devices are collectively named as S32K14X .

2.2 Overview

AUTOSAR (AUTomotive Open System ARchitecture) is an industry partnership working to establish standards for software interfaces and software modules for automobile electronic control systems.

AUTOSAR

- paves the way for innovative electronic systems that further improve performance, safety and environmental friendliness.
- is a strong global partnership that creates one common standard: "Cooperate on standards, compete on implementation".
- is a key enabling technology to manage the growing electrics/electronics complexity. It aims to be prepared for the upcoming technologies and to improve cost-efficiency without making any compromise with respect to quality.
- facilitates the exchange and update of software and hardware over the service life of the vehicle.

2.3 About this Manual

This Technical Reference employs the following typographical conventions:

Boldface type: Bold is used for important terms, notes and warnings.

Italic font: Italic typeface is used for code snippets in the text. Note that C language modifiers such "const" or "volatile" are sometimes omitted to improve readability of the presented code.

Notes and warnings are shown as below:

Note

This is a note.

2.4 Acronyms and Definitions

Table 2-2. Acronyms and Definitions

Term	Definition
BSW	Basic Software
DEM	Diagnostic Event Manager
DET	Development Error Tracer
ECU	Electronic Control Unit
ISR	interrupt Service Routine
OCU	Output Compare Unit
OS	Operating System
RAM	Random Access Memory
ROM	Read-only Memory

Table continues on the next page...

Table 2-2. Acronyms and Definitions (continued)

Term	Definition
N/A	Not Applicable
MCU	Microcontroller Unit
GUI	Graphical User Interface
EcuM	ECU state Manager
API	Application Programming Interface
PB Variant	Post Build Variant
PC Variant	Pre Compile Variant
SWS	Software Specification
VLE	Variable Length Encoding
XML	Extensible Markup Language
FTM	FlexTimer Module

2.5 Reference List

Table 2-3. Reference List

#	Title	Version
1	Specification of Ocu Driver	AUTOSAR Release 4.3.1
2	S32K14X Reference Manual	Reference Manual, Rev. 9, 9/2018
3	S32K142 Mask Set Errata for Mask 0N33V (0N33V)	30/11/2017
4	S32K144 Mask Set Errata for Mask 0N57U (0N57U)	30/11/2017
5	S32K146 Mask Set Errata for Mask 0N73V (0N73V)	30/11/2017
6	S32K148 Mask Set Errata for Mask 0N20V (0N20V)	25/10/2018
7	S32K118 Mask Set Errata for Mask 0N97V (0N97V)	07/01/2019

Chapter 3

Driver

3.1 Requirements

Requirements for this driver are detailed in the AUTOSAR 4.3 Rev0001Ocu Driver Software Specification document (See Table [Reference List](#)).

3.2 Driver Design Summary

The driver provides functions for initialization and control of the microcontroller internal OCU functionality. The OCU driver allows comparing and acting automatically when the value of a counter matches a defined threshold. The OCU driver provides services and configuration parameters for:

- Starting and stopping a comparison process
- Setting comparison threshold
- Enabling and disabling notification mechanisms
- Getting counter values
- Changing output pin states
- Triggering some hardware resources (ADC, DMA) if available

The tick duration of a channel counter depends on the channel specific settings (part of OCU driver) as well as on the system clock and settings of the clock tree controlled by the MCU module. Available FTM Clock sources can be selected in the Plugin.

The OCU driver provides an optional API and configuration parameters for changing the base clock of the controlled hardware. A dual clock functionality is offered by switching between two configured values of the clock prescaler.

For each user configured channel, a symbolic name is generated by the Tresos Studio configuration tool. The name shall be consequently used in upper applications

Interrupts can be enabled or disabled for each channel in order to have user notifications. For each channel not configured by the user in Tresos Studio configuration tool, the code for interrupt handling is removed based on a series of ifdefs.

3.3 Hardware resources

Table 3-1. OCU Hardware channels availability for S32K14X family

Device	Total FTM channels	Total External interrupt vector
Ocu_s32k142_lqfp64	30 ch, 16-bit	16 vectors
Ocu_s32k142_lqfp100	32 ch, 16-bit	16 vectors
Ocu_s32k144_lqfp64	30 ch, 16-bit	16 vectors
Ocu_s32k144_lqfp100	32 ch, 16-bit	16 vectors
Ocu_s32k144_mapbga100	32 ch, 16-bit	16 vectors
Ocu_s32k146_lqfp64	38 ch, 16-bit	21 vectors
Ocu_s32k146_lqfp100	39 ch, 16-bit	21 vectors
Ocu_s32k146_lqfp144	48 ch, 16-bit	24 vectors
Ocu_s32k146_mapbga100	39 ch, 16-bit	21 vectors
Ocu_s32k148_lqfp144	61 ch, 16-bit	32 vectors
Ocu_s32k148_lqfp176	64 ch, 16-bit	32 vectors
Ocu_s32k148_mapbga100	39 ch, 16-bit	32 vectors
Ocu_s32k118_lqfp48	39 ch, 16-bit	32 vectors
Ocu_s32k118_lqfp64	39 ch, 16-bit	32 vectors
Ocu_s32k142_lqfp48	32 ch, 16-bit	16 vectors
Ocu_s32k144_lqfp48	32 ch, 16-bit	16 vectors
Ocu_s32k148_lqfp100	39 ch, 16-bit	32 vectors

3.4 Deviation from Requirements

The driver deviates from the AUTOSAR Ocu Driver software specification in some places.

There are also some additional requirements (on top of requirements detailed in AUTOSAR Ocu Driver software specification) which need to be satisfied for correct operation.

1. Additional Requirement 1
2. Additional Requirement 2
3. Additional Requirement ...
4. Additional Requirement N

Table 3-2. Deviations Status Column Description

Term	Definition
N/A	Not available
N/T	Not testable
N/S	Out of scope
N/I	Not implemented
N/F	Not fully implemented

Below table identifies the AUTOSAR requirements that are not fully implemented, implemented differently, or out of scope for the driver.

Table 3-3. Driver Deviations Table

Requirement	Status	Description	Notes
SWS_Ocu_00005	N/A	Ocu_Lcfg.c shall include Ocu.h and Ocu_MemMap.h.	Link time config is considered an other form of Pb config. No separate files required.
SWS_Ocu_00008	N/A	Ocu_Irq.c shall include Ocu_MemMap.h and Ocu.h.	Interrupts are defined at IP layer.
SWS_Ocu_00020	N/A	The detection of production errors cannot be switched off.	DEM errors are not used
SWS_Ocu_00023	N/A	Each variable that shall be accessible by AUTOSAR Debugging, shall be defined as global variable.	AUTOSAR Debugging concept is not implemented. In par with PR-MCAL-3330
SWS_Ocu_00024	N/A	All type definitions of variables which shall be debugged shall be accessible by the header file Ocu.h.	AUTOSAR Debugging concept is not implemented. In par with PR-MCAL-3330
SWS_Ocu_00025	N/A	The declaration of variables in the header file shall be such that it is possible to calculate the size of the variables by C-"sizeof".	AUTOSAR Debugging concept is not implemented. In par with PR-MCAL-3330
SWS_Ocu_00026	N/A	Variables available for debugging shall be described in the respective OCU driver Description.	AUTOSAR Debugging concept is not implemented. In par with PR-MCAL-3330
SWS_Ocu_00125	N/A	If source code for caller and callee of Ocu_GetVersionInfo is available; the OCU driver should realize Ocu_GetVersionInfo as a macro, defined in the module's header file.	Ocu_GetVersionInfo is defined as a function as a common approach in all MCAL drivers.
SWS_Ocu_00156	N/A	These requirements are not applicable to this specification.	Not a requirement

3.5 Driver limitations

None

3.6 Driver usage and configuration tips

None.

3.7 Runtime Errors

None

3.8 Software specification

The following sections contains driver software specifications.

3.8.1 Define Reference

Constants supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.8.1.1 Define OCU_VENDOR_ID

Table 3-4. Define OCU_VENDOR_ID Description

Name	OCU_VENDOR_ID
Initializer	43

3.8.1.2 Define OCU_AR_RELEASE_MAJOR_VERSION

Table 3-5. Define OCU_AR_RELEASE_MAJOR_VERSION Description

Name	OCU_AR_RELEASE_MAJOR_VERSION
Initializer	4

3.8.1.3 Define OCU_AR_RELEASE_MINOR_VERSION

**Table 3-6. Define OCU_AR_RELEASE_MINOR_VERSION
Description**

Name	OCU_AR_RELEASE_MINOR_VERSION
Initializer	3

3.8.1.4 Define OCU_AR_RELEASE_REVISION_VERSION

**Table 3-7. Define OCU_AR_RELEASE_REVISION_VERSION
Description**

Name	OCU_AR_RELEASE_REVISION_VERSION
Initializer	1

3.8.1.5 Define OCU_SW_MAJOR_VERSION

**Table 3-8. Define OCU_SW_MAJOR_VERSION
Description**

Name	OCU_SW_MAJOR_VERSION
Initializer	1

3.8.1.6 Define OCU_SW_MINOR_VERSION

**Table 3-9. Define OCU_SW_MINOR_VERSION
Description**

Name	OCU_SW_MINOR_VERSION
Initializer	0

3.8.1.7 Define OCU_SW_PATCH_VERSION

**Table 3-10. Define OCU_SW_PATCH_VERSION
Description**

Name	OCU_SW_PATCH_VERSION
Initializer	1

3.8.1.8 Define OCU_DEINIT_ID

API service ID of Ocu_DeInit function.

Details:

Parameters used when raising an error/exception

Table 3-11. Define OCU_DEINIT_ID Description

Name	OCU_DEINIT_ID
Initializer	(0x01U)

3.8.1.9 Define OCU_DISABLENOTIFICATION_ID

API service ID of Ocu_DisableNotification function.

Details:

Parameters used when raising an error/exception

Table 3-12. Define OCU_DISABLENOTIFICATION_ID Description

Name	OCU_DISABLENOTIFICATION_ID
Initializer	(0x0AU)

3.8.1.10 Define OCU_ENABLENOTIFICATION_ID

API service ID of Ocu_EnableNotification function.

Details:

Parameters used when raising an error/exception

Table 3-13. Define OCU_ENABLENOTIFICATION_ID Description

Name	OCU_ENABLENOTIFICATION_ID
Initializer	(0x0BU)

3.8.1.11 Define OCU_GETCOUNTER_ID

API service ID of Ocu_GetCounter function.

Details:

Parameters used when raising an error/exception

Table 3-14. Define OCU_GETCOUNTER_ID Description

Name	OCU_GETCOUNTER_ID
Initializer	(0x06U)

3.8.1.12 Define OCU_GETVERSIONINFO_ID

API service ID of Ocu_GetVersionInfo function.

Details:

Parameters used when raising an error/exception

Table 3-15. Define OCU_GETVERSIONINFO_ID Description

Name	OCU_GETVERSIONINFO_ID
Initializer	(0x09U)

3.8.1.13 Define OCU_INIT_ID

API service ID of Ocu_Init function.

Details:

Parameters used when raising an error/exception

Table 3-16. Define OCU_INIT_ID Description

Name	OCU_INIT_ID
Initializer	(0x00U)

3.8.1.14 Define OCU_PROCESSNOTIFICATION_ID

API service ID.

Table 3-17. Define OCU_PROCESSNOTIFICATION_ID Description

Name	OCU_PROCESSNOTIFICATION_ID
Initializer	0x0AU

3.8.1.15 Define OCU_SETABSOLUTETHRESHOLD_ID

API service ID of Ocu_SetAbsoluteThreshold function.

Details:

Parameters used when raising an error/exception

Table 3-18. Define OCU_SETABSOLUTETHRESHOLD_ID Description

Name	OCU_SETABSOLUTETHRESHOLD_ID
Initializer	(0x07U)

3.8.1.16 Define OCU_SETCLOCKMODE_ID

API Ocu_SetClockMode service called with wrong parameter.

Details:

Parameters used when raising an error/exception

Table 3-19. Define OCU_SETCLOCKMODE_ID Description

Name	OCU_SETCLOCKMODE_ID
Initializer	(0x7AU)

3.8.1.17 Define OCU_SETPINACTION_ID

API service ID of Ocu_SetPinAction function.

Details:

Parameters used when raising an error/exception

Table 3-20. Define OCU_SETPINACTION_ID Description

Name	OCU_SETPINACTION_ID
Initializer	(0x05U)

3.8.1.18 Define OCU_SETPINSTATE_ID

API service ID of Ocu_SetPinState function.

Details:

Parameters used when raising an error/exception

Table 3-21. Define OCU_SETPINSTATE_ID Description

Name	OCU_SETPINSTATE_ID
Initializer	(0x04U)

3.8.1.19 Define OCU_SETRELATIVETHRESHOLD_ID

API service ID of Ocu_SetRelativeThreshold function.

Details:

Parameters used when raising an error/exception

Table 3-22. Define OCU_SETRELATIVETHRESHOLD_ID Description

Name	OCU_SETRELATIVETHRESHOLD_ID
Initializer	(0x08U)

3.8.1.20 Define OCU_STARTCHANNEL_ID

API service ID of Ocu_StartChannel function.

Details:

Parameters used when raising an error/exception

Table 3-23. Define OCU_STARTCHANNEL_ID Description

Name	OCU_STARTCHANNEL_ID
Initializer	(0x02U)

3.8.1.21 Define OCU_STOPCHANNEL_ID

API service ID of Ocu_StopChannel function.

Details:

Parameters used when raising an error/exception

Table 3-24. Define OCU_STOPCHANNEL_ID Description

Name	OCU_STOPCHANNEL_ID
Initializer	(0x03U)

3.8.1.22 Define OCU_E_ALREADY_INITIALIZED

API_{Ocu_Init()} called while the OCU driver has already been initialized.

Details:

Errors and exceptions that will be detected by the OCU driver.

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-25. Define OCU_E_ALREADY_INITIALIZED Description

Name	OCU_E_ALREADY_INITIALIZED
Initializer	(0x07U)

3.8.1.23 Define OCU_E_BUSY

API `Ocu_StartChannel()` called on a channel that is in state RUNNING.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-26. Define OCU_E_BUSY Description

Name	OCU_E_BUSY
Initializer	(0x09U)

3.8.1.24 Define OCU_E_INIT_FAILED

API `Ocu_Init` service called with wrong parameter.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-27. Define OCU_E_INIT_FAILED Description

Name	OCU_E_INIT_FAILED
Initializer	(0x0BU)

3.8.1.25 Define OCU_E_NO_VALID_NOTIF

Usage of `Ocu_DisableNotification()` or `Ocu_EnableNotification()` on a channel where a NULL pointer is configured as the notification function.

Details:

Errors and exceptions that will be detected by the OCU driver.

Implements: `Ocu_ErrorIds_define AUTOSAR`

Table 3-28. Define OCU_E_NO_VALID_NOTIF Description

Name	OCU_E_NO_VALID_NOTIF
Initializer	(0x06U)

3.8.1.26 Define OCU_E_PARAM_INSTANCE

Generated when the module id is more than the number of module that supported by this platform.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: `Ocu_ErrorIds_define Non-AUTOSAR`

Table 3-29. Define OCU_E_PARAM_INSTANCE Description

Name	OCU_E_PARAM_INSTANCE
Initializer	(0x1DU)

3.8.1.27 Define OCU_E_PARAM_INVALID_ACTION

API `Ocu_SetPinAction()` called with an invalid pin action.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-30. Define OCU_E_PARAM_INVALID_ACTION Description

Name	OCU_E_PARAM_INVALID_ACTION
Initializer	(0x05U)

3.8.1.28 Define OCU_E_PARAM_INVALID_CHANNEL

API service used with an invalid channel Identifier.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-31. Define OCU_E_PARAM_INVALID_CHANNEL Description

Name	OCU_E_PARAM_INVALID_CHANNEL
Initializer	(0x03U)

3.8.1.29 Define OCU_E_PARAM_INVALID_STATE

API `Ocu_SetPinState()` called with an invalid pin state or when the channel is in the RUNNING state..

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-32. Define OCU_E_PARAM_INVALID_STATE Description

Name	OCU_E_PARAM_INVALID_STATE
Initializer	(0x04U)

3.8.1.30 Define OCU_E_PARAM_INVALID_VALUE

Ocu_SetAbsoluteThreshold() Or Ocu_SetRelativeThreshold() called for with a compare match parameter greater than maximum supported counter value for a given channel.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define Non-AUTOSAR

Table 3-33. Define OCU_E_PARAM_INVALID_VALUE Description

Name	OCU_E_PARAM_INVALID_VALUE
Initializer	(0x1BU)

3.8.1.31 Define OCU_E_PARAM_NO_PIN

Ocu_SetPinState() Or Ocu_SetPinAction() called for a channel that doesn't have an associated output pin.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-34. Define OCU_E_PARAM_NO_PIN Description

Name	OCU_E_PARAM_NO_PIN
Initializer	(0x0AU)

3.8.1.32 Define OCU_E_PARAM_POINTER

API Ocu_GetVersionInfo() is called with a NULL parameter.

Details:

Errors and exceptions that will be detected by the OCU driver.

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-35. Define OCU_E_PARAM_POINTER Description

Name	OCU_E_PARAM_POINTER
Initializer	(0x08U)

3.8.1.33 Define OCU_E_UNINIT

API service used without module initialization.

Details:

Errors and exceptions that will be detected by the OCU driver

Implements: Ocu_ErrorIds_define AUTOSAR

Table 3-36. Define OCU_E_UNINIT Description

Name	OCU_E_UNINIT
Initializer	(0x02U)

3.8.1.34 Define OCU_DEINIT_API

Switch to indicate that Ocu_DeInit API is supported.

Table 3-37. Define OCU_DEINIT_API Description

Name	OCU_DEINIT_API
Initializer	(STD_ON)

3.8.1.35 Define OCU_GET_COUNTER_API

Switch to indicate that Ocu_GetCounter API is supported.

Table 3-38. Define OCU_GET_COUNTER_API Description

Name	OCU_GET_COUNTER_API
Initializer	(STD_ON)

3.8.1.36 Define OCU_SET_ABSOLUTE_THRESHOLD_API

Switch to indicate that Ocu_SetAbsoluteThreshold API is supported.

Table 3-39. Define OCU_SET_ABSOLUTE_THRESHOLD_API Description

Name	OCU_SET_ABSOLUTE_THRESHOLD_API
Initializer	(STD_ON)

3.8.1.37 Define OCU_SET_CLOCK_MODE_API

Switch for enabling the dual clock functionality (Ocu_SetClockMode API).

Table 3-40. Define OCU_SET_CLOCK_MODE_API Description

Name	OCU_SET_CLOCK_MODE_API
Initializer	(STD_OFF)

3.8.1.38 Define OCU_SET_PIN_ACTION_API

Switch to indicate that Ocu_SetPinAction API is supported.

Table 3-41. Define OCU_SET_PIN_ACTION_API Description

Name	OCU_SET_PIN_ACTION_API
Initializer	(STD_ON)

3.8.1.39 Define OCU_SET_PIN_STATE_API

Switch to indicate that Ocu_SetPinState API is supported.

Table 3-42. Define OCU_SET_PIN_STATE_API Description

Name	OCU_SET_PIN_STATE_API
Initializer	(STD_ON)

3.8.1.40 Define OCU_SET_RELATIVE_THRESHOLD_API

Switch to indicate that Ocu_SetRelativeThreshold API is supported.

Table 3-43. Define OCU_SET_RELATIVE_THRESHOLD_API Description

Name	OCU_SET_RELATIVE_THRESHOLD_API
Initializer	(STD_ON)

3.8.1.41 Define OCU_VERSION_INFO_API

Switch to indicate that Ocu_GetVersionInfo API is supported.

Table 3-44. Define OCU_VERSION_INFO_API Description

Name	OCU_VERSION_INFO_API
Initializer	(STD_ON)

3.8.1.42 Define OCU_NOTIFICATION_SUPPORTED

Switch to indicate that the notifications are supported.

Table 3-45. Define OCU_NOTIFICATION_SUPPORTED Description

Name	OCU_NOTIFICATION_SUPPORTED
Initializer	(STD_ON)

3.8.1.43 Define OCU_DEV_ERROR_DETECT

Switch for enabling the development error detection.

Table 3-46. Define OCU_DEV_ERROR_DETECT Description

Name	OCU_DEV_ERROR_DETECT
Initializer	(STD_ON)

3.8.2 Enum Reference

Enumeration of all constants supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.8.2.1 Enumeration Ocu_ChannelStatusType

This enumerated type allows the selection of channel status type.

Table 3-47. Enumeration Ocu_ChannelStatusType Values

Name	Initializer	Description
OCU_STATUS_UNINITIALIZED	0	OCU channel status - uninitialized.
OCU_STATUS_INITIALIZED	1	OCU channel status - initialized.
OCU_STATUS_STOPPED	2	OCU channel status - stopped.
OCU_STATUS_RUNNING	3	OCU channel status - expired.

3.8.2.2 Enumeration Ocu_CountDirectionType

Ocu Count direction.

Details:

This enum specifies the count direction for the whole OCU driver.

Implements: Ocu_CountDirectionType_enumeration

Table 3-48. Enumeration Ocu_CountDirectionType Values

Name	Initializer	Description
OCU_UPCOUNTING	0	Counter in UP Counting.
OCU_DOWNCOUNTING	1	Counter in DOWN Counting.

3.8.2.3 Enumeration Ocu_GlobalStateType

Enum containing the possible states of the Ocu driver.

Table 3-49. Enumeration Ocu_GlobalStateType Values

Name	Initializer	Description
OCU_STATE_UNINIT	0x00	OCU STATE UNINIT
OCU_STATE_IDLE	0x01	OCU STATE IDLE

3.8.2.4 Enumeration Ocu_PinActionType

Edge Pin Action type.

Details:

Automatic action (by hardware) to be performed on a pin attached to an OCU channel.

Implements: Ocu_PinActionType_enumeration

Table 3-50. Enumeration Ocu_PinActionType Values

Name	Initializer	Description
OCU_SET_LOW	0	The channel pin will be set HIGH upon compare match.
OCU_SET_HIGH	1	The channel pin will be set LOW upon compare match.
OCU_TOGGLE	2	The channel pin will be set to the opposite of its current level HIGH upon compare match.
OCU_DISABLE	3	The channel pin will remain at its current level upon compare match.

3.8.2.5 Enumeration Ocu_PinStateType

Pin State level.

Details:

Output state of the pin linked to an OCU channel.

Implements: Ocu_PinStateType_enumeration

Table 3-51. Enumeration Ocu_PinStateType Values

Name	Initializer	Description
OCU_LOW	0	Ocu Pin level is logic low.
OCU_HIGH	1	Ocu Pin level is logic high.

3.8.2.6 Enumeration Ocu_ReturnType

Ocu Return Type.

Details:

Return information after setting a new threshold value.

Implements: Ocu_PinStateType_enumeration

Table 3-52. Enumeration Ocu_ReturnType Values

Name	Initializer	Description
OCU_CM_IN_REF_INTERVAL	0	The compare match will occur inside the current Reference Interval.
OCU_CM_OUT_REF_INTERVAL	1	The compare match will not occur inside the current Reference Interval.

3.8.2.7 Enumeration Ocu_SelectPrescalerType

Prescaler type.

Details:

This enum specifies the possible types of prescallers used to configure base-clock timers

Table 3-53. Enumeration Ocu_SelectPrescalerType Values

Name	Initializer	Description
OCU_PRIMARY_PRESCALER	0	Selected value is the default/primary prescaler.
OCU_ALTERNATIVE_PRESCALER	1	Selected value is the alternative configured prescaler.

3.8.3 Function Reference

Functions of all functions supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.8.3.1 Function Ocu_Init

This function initializes the Ocu driver.

Details:

This service is a non reentrant function used for driver initialization. The Initialization function shall initialize all relevant registers of the configured hardware with the values of the structure referenced by the parameter ConfigPtr. If the hardware allows for only one usage of the register, the driver module implementing that functionality is responsible for initializing the register. The initialization function of this module shall always have a pointer as a parameter, even though for Variant PC no configuration set shall be given. Instead a NULL pointer shall be passed to the initialization function. The Ocu module environment shall not call Ocu_Init during a running operation (e. g. when Ocu_StartChannel is called).

Return: void.

Implements: Ocu_Init_Activity

Violates: Violates MISRA 2004 Required Rule 8.10 could be made static

Prototype: void Ocu_Init(const Ocu_ConfigType *ConfigPtr);

Table 3-54. Ocu_Init Arguments

Type	Name	Direction	Description
constOcu_ConfigType*	ConfigPtr	input	Pointer to OCU top configuration structure.

3.8.3.2 Function Ocu_DeInit

This function deinitializes the Ocu driver.

Details:

The function `Ocu_DeInit` shall deinitialize the OCU module.

The function `Ocu_DeInit` shall deinitialize the OCU variables and registers that were initialized by `Ocu_Init` to a state comparable to their power on reset state. The function `Ocu_DeInit` shall disable OCU interrupts and OCU signal edge notifications. The function `Ocu_DeInit` shall stop all free-running counters, which are exclusively used by this driver. If development error detection for the Ocu module is enabled, when a development error occurs, the corresponding OCU function shall:

- Report the error to the Development Error Tracer.
- Skip the desired functionality in order to avoid any corruptions of data or hardware registers (this means leave the function without any actions). If development error detection is enabled for the OCU driver: if a channel is still in the RUNNING state when the function `Ocu_DeInit` is called, then the function shall raise the development error 'OCU_E_PARAM_INVALID_STATE' and return without any action. If development error detection for the Ocu module is enabled, if any function (except `Ocu_Init`) is called before `Ocu_Init` has been called, the called function shall raise development error `OCU_E_UNINIT`.

Return: void.

Implements: `Ocu_DeInit_Activity`

Prototype: `void Ocu_DeInit(void);`

3.8.3.3 Function `Ocu_GetVersionInfo`

This function returns Ocu driver version details.

Details:

The function `Ocu_GetVersionInfo` shall return the version information of this module. The version information includes: Module Id, Vendor Id, Vendor specific version number.

Return: void.

Implements: `Ocu_GetVersionInfo_Activity`

Prototype: `void Ocu_GetVersionInfo(Std_VersionInfoType *versioninfo);`

Table 3-55. Ocu_GetVersionInfo Arguments

Type	Name	Direction	Description
Std_VersionInfoType *	versioninfo	input, output	- pointer to Std_VersionInfoType output variable.

3.8.3.4 Function Ocu_DisableNotification

This service is used to disable notifications from an OCU channel.

Details:

The function Ocu_DisableNotification shall disable the OCU compare match notification.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function Ocu_DisableNotification shall raise the error OCU_E_UNINIT and return without any action.

If development error detection is enabled for the OCU driver: If the parameter Channel is invalid (not within the range specified by configuration), the function Ocu_DisableNotification shall raise the error OCU_E_PARAM_INVALID_CHANNEL and return without any action.

If development error detection is enabled for the OCU driver: If the notification function is the NULL pointer, the function Ocu_DisableNotification shall raise the error OCU_E_NO_VALID_NOTIF and return without any action.

Return: void.

Implements: Ocu_DisableNotification_Activity

Prototype: void Ocu_DisableNotification(Ocu_ChannelType ChannelNumber);

Table 3-56. Ocu_DisableNotification Arguments

Type	Name	Direction	Description
Ocu_ChannelType	ChannelNumber	input	- Ocu channel id.

3.8.3.5 Function Ocu_EnableNotification

This service is used to enable notifications from an OCU channel.

Details:

The function `Ocu_EnableNotification` shall enable the OCU compare match notification of the indexed channel.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function `Ocu_EnableNotification` shall raise the error `OCU_E_UNINIT` and return without any action.

If development error detection is enabled for the OCU driver: If the parameter `Channel` is invalid (not within the range specified by configuration), then the function `Ocu_EnableNotification` shall raise the error `OCU_E_PARAM_INVALID_CHANNEL` and return without any action.

If development error detection is enabled for the OCU driver: If the notification function is the `NULL` pointer, the function `Ocu_EnableNotification` shall raise the error `OCU_E_NO_VALID_NOTIF` and return without any action.

Return: `void`.

Implements: `Ocu_EnableNotification_Activity`

Prototype: `void Ocu_EnableNotification(Ocu_ChannelType ChannelNumber);`

Table 3-57. Ocu_EnableNotification Arguments

Type	Name	Direction	Description
<code>Ocu_ChannelType</code>	<code>ChannelNumber</code>	input	- Ocu channel id.
	<code>Notification</code>	input	- notification type to be enabled.

3.8.3.6 Function `Ocu_StartChannel`

This function starts a specified Ocu channel.

Details:

The function `Ocu_StartChannel` shall start an OCU channel by allowing all compare match configured actions to be performed.

The state of the selected channel shall be set to “RUNNING” If the function `Ocu_StartChannel` has been successfully performed.

If development error detection is enabled for the OCU driver: If the function `Ocu_StartChannel` is called on a channel in the state "RUNINNG", then the function shall raise the error `OCU_E_BUSY` and return without any action.

If development error detection is enabled for the OCU driver: If the parameter `ChannelNumber` is invalid (not within the range specified by the configuration), the function `Ocu_StartChannel` shall raise the error `OCU_E_PARAM_INVALID_CHANNEL` and return without any action.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function `Ocu_StartChannel` shall raise the error `OCU_E_UNINIT` and return without any action.

Return: void.

Implements: `Ocu_StartChannel_Activity`

Prototype: `void Ocu_StartChannel(Ocu_ChannelType ChannelNumber);`

Table 3-58. Ocu_StartChannel Arguments

Type	Name	Direction	Description
<code>Ocu_ChannelType</code>	<code>ChannelNumber</code>	input	Ocu channel id.

3.8.3.7 Function `Ocu_StopChannel`

This function stops a specified Ocu channel.

Details:

The function `Ocu_StopChannel` shall stop an OCU channel by halting compare match configured actions for this channel.

The state of the selected channel shall be set to "STOPPED" if the function `Ocu_StopChannel` is successfully performed. If the function `Ocu_StopChannel` is called on a channel in the state "STOPPED", then the function shall leave without any action (no change of the channel state), and shall not raise a development error.

If development error detection is enabled for the OCU driver: If the parameter `ChannelNumber` is invalid (not within the range specified by the configuration), the function `Ocu_StopChannel` shall raise the error `OCU_E_PARAM_INVALID_CHANNEL` and return without any action.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function `Ocu_StopChannel` shall raise the error `OCU_E_UNINIT` and return without any action.

Return: void.

Implements: `Ocu_StopChannel_Activity`

Prototype: `void Ocu_StopChannel(Ocu_ChannelType ChannelNumber);`

Table 3-59. Ocu_StopChannel Arguments

Type	Name	Direction	Description
<code>Ocu_ChannelType</code>	<code>ChannelNumber</code>	input	- Ocu channel id.

3.8.3.8 Function `Ocu_SetPinState`

Service to set immediately the level of the pin associated to an OCU channel.

Details:

The function `Ocu_SetPinState` shall set the pin associated with the channel to the level indicated by “PinState”.

The function `Ocu_SetPinState` shall be used only if the channel is not in the RUNNING state.

If development error detection is enabled for the OCU driver: If the parameter `ChannelNumber` is invalid (not within the range specified by the configuration), the function `Ocu_SetPinState` shall raise the error `OCU_E_PARAM_INVALID_CHANNEL` and return without any action

If development error detection is enabled for the OCU driver: If a pin is not associated with the channel (not defined in the configuration of the channel), the function `Ocu_SetPinState` shall raise the error `OCU_E_PARAM_NO_PIN` and return without any action.

If development error detection is enabled for the OCU driver: If the parameter `PinState` is invalid (not within the range specified by the configuration), the function `Ocu_SetPinState` shall raise the error `OCU_E_PARAM_INVALID_STATE` and return without any action.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function `Ocu_SetPinState` shall raise the error `OCU_E_UNINIT` and return without any action.

If development error detection is enabled for the OCU driver: If the channel is in the `RUNNING` state, the function `Ocu_SetPinState` shall raise the error `OCU_E_PARAM_INVALID_STATE` and return without any action.

Return: void.

Implements: `Ocu_SetPinState_Activity`

Prototype: `void Ocu_SetPinState(Ocu_ChannelType ChannelNumber, Ocu_PinStateType PinState);`

Table 3-60. Ocu_SetPinState Arguments

Type	Name	Direction	Description
<code>Ocu_ChannelType</code>	<code>ChannelNumber</code>	input	- Ocu channel id.
<code>Ocu_PinStateType</code>	<code>PinState</code>	input	- Output Pin State.

3.8.3.9 Function `Ocu_SetPinAction`

Service to indicate the driver what shall be done automatically by hardware (if supported) upon compare match.

Details:

The function `Ocu_SetPinAction` shall set the action to be performed by hardware automatically, at the next compare match in the corresponding OCU channel.

If development error detection is enabled for the OCU driver: If the parameter `ChannelNumber` is invalid (not within the range specified by the configuration), the function `Ocu_SetPinAction` shall raise the error `OCU_E_PARAM_INVALID_CHANNEL` and return without any action.

If development error detection is enabled for the OCU driver: If a pin is not associated with the channel (not defined in the configuration of the channel), the function `Ocu_SetPinAction` shall raise the error `OCU_E_PARAM_NO_PIN` and return without any action.

If development error detection is enabled for the OCU driver: If the parameter PinAction is invalid (not within the range specified by the type), the function Ocu_SetPinAction shall raise the error OCU_E_PARAM_INVALID_ACTION and return without any action.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function Ocu_SetPinAction shall raise the error OCU_E_UNINIT and return without any action.

If a pin is associated with a channel; the relevant action with this pin shall be performed upon compare match.

Return: void.

Implements: Ocu_SetPinAction_Activity

Prototype: void Ocu_SetPinAction(Ocu_ChannelType ChannelNumber, Ocu_PinActionType PinAction);

Table 3-61. Ocu_SetPinAction Arguments

Type	Name	Direction	Description
Ocu_ChannelType	ChannelNumber	input	- Ocu channel id.
Ocu_PinActionType	PinAction	input	- Pin Action (OCU_SET_LOW, OCU_SET_HIGH, OCU_TOGGLE, OCU_DISABLE).

3.8.3.10 Function Ocu_GetCounter

Service to read the current value of the counter.

Details:

The function Ocu_GetCounter shall read and return the value of the counter of the channel indicated by ChannelNumber.

If development error detection is enabled for the OCU driver: If the parameter ChannelNumber is invalid (not within the range specified by the configuration), the function Ocu_GetCounter shall raise the error OCU_E_PARAM_INVALID_CHANNEL and shall return the value “0”.

If development error detection is enabled for the OCU driver: if the driver is not initialized, then the function Ocu_GetCounterValue shall raise the error OCU_E_UNINIT and shall return the value “0”.

Return: Ocu_ValueType the value of the hardware counter.

Implements: Ocu_GetCounter_Activity

Prototype: Ocu_ValueType Ocu_GetCounter(Ocu_ChannelType ChannelNumber);

Table 3-62. Ocu_GetCounter Arguments

Type	Name	Direction	Description
Ocu_ChannelType	ChannelNumber	input	- Ocu channel id.

3.8.3.11 Function Ocu_SetAbsoluteThreshold

Service to set the value of the channel threshold using an absolute input data.

Details:

The function Ocu_SetAbsoluteThreshold shall set the channel threshold (the compare value) to the value given by AbsoluteValue.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function Ocu_SetAbsoluteThreshold shall raise the error OCU_E_UNINIT and return without any action.

If development error detection is enabled for the OCU driver: If the parameter ChannelNumber is invalid (not within the range specified by the configuration), the function Ocu_SetAbsoluteThreshold shall raise the error OCU_E_PARAM_INVALID_CHANNEL and return without any action.

After setting a new threshold value, the API Ocu_SetAbsoluteThreshold shall return a status to inform the caller whether the compare match will occur (or has already occurred) during the current Reference Interval, as a result of setting the new threshold value. (see OCU_SWS for details)

Return: Ocu_ReturnType - Tells the caller whether the compare match will occur (or has already occurred) during the current Reference Interval, as a result of setting the new threshold value.

Implements: Ocu_SetAbsoluteThreshold_Activity

Prototype: Ocu_ReturnType Ocu_SetAbsoluteThreshold(Ocu_ChannelType ChannelNumber, Ocu_ValueType ReferenceValue, Ocu_ValueType AbsoluteValue);

Table 3-63. Ocu_SetAbsoluteThreshold Arguments

Type	Name	Direction	Description
Ocu_ChannelType	ChannelNumber	input	- Ocu channel id.
Ocu_ValueType	ReferenceValue	input	- Value given by the upper layer and used as a base to determine whether to call the notification before the function exits or not.
Ocu_ValueType	AbsoluteValue	input	- Value to compare with the content of the counter. This value is in ticks.

3.8.3.12 Function Ocu_SetRelativeThreshold

Service to set the value of the channel threshold relative to the current value of the counter.

Details:

The function Ocu_SetAbsoluteThreshold shall set the channel threshold (the compare value) to the value given by RelativeValue plus the current counter value read from hw.

After setting a new threshold value, the API Ocu_SetRelativeThreshold shall return a status to inform the caller whether the compare match will occur (or has already occurred) during the current Reference Interval, as a result of setting the new threshold value.

If development error detection is enabled for the OCU driver: If the driver is not initialized, the function Ocu_SetRelativeThreshold shall raise the error OCU_E_UNINIT and return without any action.

After setting a new threshold value, the API Ocu_SetRelativeThreshold shall return a status to inform the caller whether the compare match will occur (or has already occurred) during the current Reference Interval, as a result of setting the new threshold value.

Return: Ocu_ReturnType - Tells the caller whether the compare match will occur (or has already occurred) during the current Reference Interval, as a result of setting the new threshold value.

Implements: Ocu_SetRelativeThreshold_Activity

Prototype: Ocu_ReturnType Ocu_SetRelativeThreshold(Ocu_ChannelType ChannelNumber, Ocu_ValueType RelativeValue);

Table 3-64. Ocu_SetRelativeThreshold Arguments

Type	Name	Direction	Description
Ocu_ChannelType	ChannelNumber	input	- Ocu channel id.
Ocu_ValueType	RelativeValue	input	- Value to use for computing the new threshold.

3.8.3.13 Function Ocu_SetClockMode

This function sets the clock mode for the driver

Details:

This function is reentrant and it changes the prescaler for the driver, changing the power consumption of the driver

Return: void.

Pre: Ocu_Init must be called before.

Implements: Ocu_SetClockMode_Activity

Violates: Violates MISRA 2004 Required Rule 8.10 could be made static

Prototype: void Ocu_SetClockMode(Ocu_SelectPrescalerType Prescaler);

Table 3-65. Ocu_SetClockMode Arguments

Type	Name	Direction	Description
Ocu_SelectPrescalerType	Prescaler	input	Prescaler type: Normal or Alternate

3.8.4 Structs Reference

Data structures supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.8.4.1 Structure Ocu_ConfigType

Structure that contains OCU channel configuration.

Details:

It contains the information like Ocu Channel Numbers, Ocu Channel Configuration Module hardware configuration.

Implements: Ocu_ConfigType_struct

Declaration:

```
typedef struct
{
    Ocu_ChannelType nNumChannels,
    Ocu_ChannelConfigType pOcuChannelsConfig,
    Ocu_IpConfigType IpConfig,
    Ocu_ChannelType HwToLogicChannelMap[]
} Ocu_ConfigType;
```

Table 3-66. Structure Ocu_ConfigType member description

Member	Description
nNumChannels	Number of channels for a given configuration
pOcuChannelsConfig	Pointer to the array of channels configured
IpConfig	structure of the IP Configuration data
HwToLogicChannelMap[]	Array for the hardware channel to logical channel mapping. It's used during the notification callback from the ISR

3.8.4.2 Structure Ocu_ChannelConfigType

Structure that contains OCU channel configuration.

Details:

It contains the information like Ocu Output Pin Enabled

Implements: Ocu_ChannelConfigType_struct

Declaration:

```
typedef struct
{
    boolean bOcuOutputPinEnable,
    Ocu_NotifyType pfOcuChannelNotification
} Ocu_ChannelConfigType;
```

Table 3-67. Structure Ocu_ChannelConfigType member description

Member	Description
bOcuOutputPinEnable	The measurement mode for a channel (Timestamp, Signal Measurement, Signal Edge Detect, Edge Counter)
pfOcuChannelNotification	The configured notification for OcuChannel

3.8.4.3 Structure Ocu_IpConfigType

Structure that contains Ocu parameters. It represents a link from the logical configuration to the hardware config.

Implements: Ocu_IpConfigType_struct

Declaration:

```
typedef struct
{
    Ocu_Ftm_IpConfigType pFtmIpConfig,
    Ocu_IpChannelConfigType (*pIpChannelsConfig)[]
} Ocu_IpConfigType;
```

Table 3-68. Structure Ocu_IpConfigType member description

Member	Description
pFtmIpConfig	Pointer to the FTM IP configuration
(*pIpChannelsConfig)[];	Array of the configured hardware channel

3.8.4.4 Structure Ocu_IpChannelConfigType

Structure that combine configuration of each FTM channels in the Ocu.

Implements: Ocu_IpChannelConfigType_struct

Declaration:

```
typedef struct
{
    uint8 u8IdxChannelConfig
} Ocu_IpChannelConfigType;
```

Table 3-69. Structure Ocu_IpChannelConfigType member description

Member	Description
u8IdxChannelConfig	Assigned FTM channel id.

3.8.4.5 Structure Ocu_Ftm_IpConfigType

Structure that contains the Ocu general IP configuration.

Implements: Ocu_Ftm_IpConfigType

Declaration:

```
typedef struct
{
    Ocu_Ftm_ChannelType u8NumChannels,
    Ocu_Ftm_ModuleType u8NumModules,
    Ocu_Ftm_ChannelConfigType (*pChannelsConfig) [],
    Ocu_Ftm_ModuleConfigType (*pModulesConfig) [];
} Ocu_Ftm_IpConfigType;
```

Table 3-70. Structure Ocu_Ftm_IpConfigType member description

Member	Description
u8NumChannels	Number of the hardware configured channels
u8NumModules	Number of the hardware configured modules
(*pChannelsConfig)[];	List of the hardware channel configurations
(*pModulesConfig)[];	List of the hardware module configurations

3.8.4.6 Structure Ocu_Ftm_ChannelConfigType

Structure that contains the Ocu general IP configuration.

Implements: Ocu_Ftm_ChannelConfigType

Declaration:

```
typedef struct
{
    Ocu_Ftm_ChannelType u8EncodedHwChannel,
    Ocu_ValueType u16DefaultThreshold;
    Ocu_Ftm_ChannelControlType u8ChannelControlValue;
} Ocu_Ftm_ChannelConfigType;
```

Table 3-71. Structure Ocu_Ftm_ChannelConfigType member description

Member	Description
u8EncodedHwChannel	NAssigned Ftm channel id
u16DefaultThreshold	Compare match threshold for the current channe
u8ChannelControlValue	Ftm channel parameters : Bits 7 --> 1: Output Pin is Used / 0: Output Pin is not used

Table 3-71. Structure Ocu_Ftm_ChannelConfigType member description

Member	Description
	Bit 6 --> Default Pin State: 0: PIN_LOW; 1: PIN_HIGH Bits 5 .. 4 --> Pin Action behaviour on compare match: SET_PIN_LOW; 2: SET_PIN_HIGH; 1: PIN_TOGGLE; 0: OUTPUT_DISABLE Bits 3 .. 0 --> Reserved for future use

3.8.4.7 Structure Ocu_Ftm_ModuleConfigType

Structure that contains the Ocu general IP configuration.

Implements: Ocu_Ftm_ModuleConfigType

Declaration:

```
typedef struct
{
    uint8 u8ModuleId,
    uint16 u16MaxCounterValue;
    Ocu_Ftm_ModuleControlType u8ModuleControlValue;
    #if (OCU_SET_CLOCK_MODE_API == STD_ON)
    uint8 u8AltControlValue;
    #endif
} Ocu_Ftm_ModuleConfigType;
```

Table 3-72. Structure Ocu_Ftm_ModuleConfigType member description

Member	Description
u8ModuleId	Assigned Ftm module id
u16MaxCounterValue	Maximum counter value
u8ModuleControlValue	Ftm module parameters : Bits 7 .. 6 --> Clock source Bits 5 .. 3 --> Normal prescale Bit 2 .. 1 --> Debug mode config Bits 0 --> Reserved for future use
u8AltControlValue	Ftm channel parameters : Bits 7 .. 5 --> Alternate Prescaler configuration Bits 4 .. 0 --> Reserved for future use

3.8.5 Types Reference

Types supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.8.5.1 Typedef Ocu_ChannellpType

IP type used to implement a Ocu channel.

Type: uint8

3.8.5.2 Typedef Ocu_ChannelType

Ocu channel type.

Implements: Ocu_ChannelType_typedef

Type: uint16

3.8.5.3 Typedef Ocu_Ftm_ChannelType

Ftm HW module/channel id type

Type: uint8

3.8.5.4 Typedef Ocu_Ftm_ModuleType

Ftm HW module/channel id type

Type: uint8

3.8.5.5 Typedef Ocu_Ftm_ChannelControlType

Ftm unified channel control register value

Type: uint8

3.8.5.6 Typedef Ocu_Ftm_ModuleControlType

Ftm unified module control register value

Type: uint8

3.8.5.7 Typedef Ocu_NotifyType

Channel notification typedef.

Type: void(*)

3.8.5.8 Typedef Ocu_ValueType

Ocu Value type (the value of the period is platform dependent and thus configurable).

Implements: Ocu_ValueType_typedef

Type: uint16

3.8.6 Variables Reference

Variables supported by the driver are as per AUTOSAR Ocu Driver software specification Version 4.3 Rev0001 .

3.9 Symbolic Names Disclaimer

All containers having the symbolic name tag set as true in the Autosar schema will generate defines like:

```
#define <Container_Short_Name> <Container_ID>
```

For this reason it is forbidden to duplicate the name of such containers across the MCAL configuration, or to use names that may trigger other compile issues (e.g. match existing #ifdefs arguments).

Chapter 4

Tresos Configuration Plug-in

This chapter describes the Tresos configuration plug-in for the Ocu Driver. The most of the parameters are described below.

4.1 Configuration elements of Ocu

Included forms :

- IMPLEMENTATION_CONFIG_VARIANT
- OcuConfigurationOfOptApiServices
- OcuGeneral
- CommonPublishedInformation
- OcuGeneral

4.2 Form IMPLEMENTATION_CONFIG_VARIANT



Figure 4-1. Tresos Plugin snapshot for IMPLEMENTATION_CONFIG_VARIANT form.

Table 4-1. Attribute IMPLEMENTATION_CONFIG_VARIANT detailed description

Property	Value
Label	Config Variant
Default	VariantPostBuild
Range	VariantPostBuild VariantPreCompile

4.3 Form OcuConfigurationOfOptionalApis




Figure 4-2. Tresos Plugin snapshot for OcuConfigurationOfOptionalApis form.

4.3.1 OcuDeInitApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_DeInit() from the code.

Table 4-2. Attribute OcuDeInitApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.2 OcuGetCounterApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_GetCounter() from the code.

Table 4-3. Attribute OcuGetCounterApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.3 OcuNotificationSupported (OcuConfigurationOfOptionalApis)

Adds / removes the services Ocu_EnableNotification() and Ocu_DisableNotification() from the code.

Table 4-4. Attribute OcuNotificationSupported (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.4 OcuSetAbsoluteThresholdApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_SetAbsoluteThreshold() from the code.

Table 4-5. Attribute OcuSetAbsoluteThresholdApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.5 OcuSetPinActionApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_SetPinAction() from the code.

Table 4-6. Attribute OcuSetPinActionApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.6 OcuSetPinStateApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_SetPinState() from the code.

Table 4-7. Attribute OcuSetPinStateApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.7 OcuSetRelativeThresholdApi (OcuConfigurationOfOptionalApis)

Adds / removes the service Ocu_SetRelativeThreshold() from the code.

Table 4-8. Attribute OcuSetRelativeThresholdApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.3.8 OcuVersionInfoApi (OcuConfigurationOfOptionalApis)

Switch to indicate that the Ocu_GetVersionInfo() is supported.

Table 4-9. Attribute OcuVersionInfoApi (OcuConfigurationOfOptionalApis) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false

4.4 Form OcuGeneral

This container contains the module-wide configuration (parameters) of the OCU Driver.




Figure 4-3. Tresos Plugin snapshot for OcuGeneral form.

4.4.1 OcuDevErrorDetect (OcuGeneral)

Enables/Disables development error detection.

Table 4-10. Attribute OcuDevErrorDetect (OcuGeneral) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	true

4.4.2 OcuEnableDualClockMode (OcuGeneral)

Enables/Disables API Ocu_SetClockMode().

Table 4-11. Attribute OcuEnableDualClockMode (OcuGeneral) detailed description

Property	Value
Type	BOOLEAN
Origin	Custom
Default	false

4.4.3 OcuEnableUserModeSupport (OcuGeneral)


When this parameter is enabled, the Ocu module will adapt to run from User Mode. Ocu driver does not perform any further actions when running in User Mode. Note: Implementation Specific Parameter.

Table 4-12. Attribute OcuEnableDualClockMode (OcuGeneral) detailed description

Property	Value
Type	BOOLEAN
Origin	Custom
Default	false

4.4.4 Form OcuHwResourceConfig

This container contains list of available interrupt sources supported by hardware. This tab also enables or disables interrupts for channels which are used in application.

**Figure 4-4. TresoS Plugin snapshot for OcuHwResourceConfig form.**

4.4.4.1 OculsrHwId (OcuHwResourceConfig)

Id of the HW interrupt service routine available platform wide and usable by the Ocu module

Table 4-13. Attribute OculsrHwId (OcuGeneral) detailed description

Property	Value
Type	STRING
Origin	Custom
Symbolic Name	false
Range	FTM_0_CH_0,FTM_0_CH_1,FTM_0_CH_2,FTM_0_CH_3,FTM_0_CH_4,FTM_0_CH_5,FTM_0_CH_6,FTM_0_CH_7,FTM_1_CH_0,FTM_1_CH_1,FTM_1_CH_2,FTM_1_CH_3,FTM_1_CH_4,FTM_1_CH_5,FTM_1_CH_6,FTM_1_CH_7,FTM_2_CH_0,FTM_2_CH_1,FTM_2_CH_2,FTM_2_CH_3,FTM_2_CH_4,FTM_2_CH_5,FTM_2_CH_6,FTM_2_CH_7,FTM_3_CH_0,FTM_3_CH_1,FTM_3_CH_2,FTM_3_CH_3,FTM_3_CH_4,FTM_3_CH_5,FTM_3_CH_6,FTM_3_CH_7,FTM_4_CH_0,FTM_4_CH_1,FTM_4_CH_2,FTM_4_CH_3,FTM_4_CH_4,FTM_4_CH_5,FTM_4_CH_6,FTM_4_CH_7,FTM_5_CH_0,FTM_5_CH_1,FTM_5_CH_2,FTM_5_CH_3,FTM_5_CH_4,FTM_5_CH_5,F

Table 4-13. Attribute OculsrHwId (OcuGeneral) detailed description

Property	Value
	TM_5_CH_6,FTM_5_CH_7,FTM_6_CH_0,FTM_6_CH_1,FTM_6_CH_2,FTM_6_CH_3,FTM_6_CH_4,FTM_6_CH_5,FTM_6_CH_6,FTM_6_CH_7,FTM_7_CH_0,FTM_7_CH_1,FTM_7_CH_2,FTM_7_CH_3,FTM_7_CH_4,FTM_7_CH_5,FTM_7_CH_6,FTM_7_CH_7

4.4.4.2 OculsrEnable (OcuHwResourceConfig)

Status of the HW Interrupt (true - Interrupt shall be enable platform wide; false - Interrupt shall be disabled platform wide.

Table 4-14. Attribute OculsrEnable (OcuGeneral) detailed description

Property	Value
Type	BOOLEAN
Origin	Custom
Symbolic Name	false
Default	false

4.4.4.3 OcuChannellsUsed (OcuHwResourceConfig)

This column configures HW channels which are going to be used.

Table 4-15. Attribute OcuChannellsUsed (OcuGeneral) detailed description

Property	Value
Type	BOOLEAN
Origin	Custom
Symbolic Name	false
Default	false

4.5 Form OcuConfigSet

This container is the base of a Configuration Set, which contains the configured OCU channels. This way, different configuration sets can be defined for post-build process

The screenshot shows the Tresos Plugin interface for the OcuConfigSet form. At the top, there is a section titled 'OcuConfigSet'. Below this, there is a 'Name' field with a folder icon and the text 'OcuConfigSet'. Below the 'Name' field, there is a section for 'OcuCountdirection' with a checkbox icon and a dropdown menu showing 'OCU_UPCOUNTING'.

Figure 4-5. Tresos Plugin snapshot for OcuConfigSet form.

4.5.1 OcuCountdirection (OcuConfigSet)

This parameter indicates the count direction for the whole OCU driver.

Table 4-16. Attribute OcuCountdirection (OcuConfigSet) detailed description

Property	Value
Type	ENUMERATION
Origin	AUTOSAR_ECUC
Optional	true
Default	OCU_UPCOUNTING
Range	OCU_UPCOUNTING OCU_DOWNCOUNTING

4.5.2 Form OcuChannel

This container contains the channel-wide configuration (parameters) of the OCU Driver

Is included by form : [Form OcuConfigSet](#)




Figure 4-6. Tresos Plugin snapshot for OcuChannel form.

4.5.2.1 OcuChannelId (OcuChannel)

Channel Id of the OCU channel. This value will be assigned to the symbolic name derived of the OcuChannel container short name.

Table 4-17. Attribute OcuChannelId (OcuChannel) detailed description

Property	Value
Type	INTEGER
Origin	AUTOSAR_ECUC
Symbolic Name	true
Invalid	Range <=65535 >=0

4.5.2.2 OcuAssignedHardwareChannel (OcuChannel)

The physical hardware channel that is assigned to this logical channel.

Table 4-18. Attribute OcuAssignedHardwareChannel (OcuChannel) detailed description

Property	Value
Type	INTEGER

Table continues on the next page...

Table 4-18. Attribute OcuAssignedHardwareChannel (OcuChannel) detailed description (continued)

Property	Value
Origin	AUTOSAR_ECUC
Symbolic Name	false
Range	<=255 >=0

4.5.2.3 FtmHwChannel (OcuChannel)

The Ftm hardware channel that is assigned to this logical channel.

Table 4-19. Attribute FtmHwChannel (OcuChannel) detailed description

Property	Value
Type	STRING
Origin	Custom
Symbolic Name	false
Optional	true

4.5.2.4 OcuDefaultThreshold (OcuChannel)

Value of comparison threshold used for Initialization.

Table 4-20. Attribute OcuDefaultThreshold (OcuChannel) detailed description

Property	Value
Type	ENUMERATION
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	10000
Range	<=65535 >=0

4.5.2.5 OcuMaxCounterValue (OcuChannel)

Maximum value in ticks, the counter of the OCU channel is able to count.

Table 4-21. Attribute OcuMaxCounterValue (OcuChannel) detailed description

Property	Value
Type	AUTOSAR_ECUC
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	65535
Invalid	Range <=65535 >=0

4.5.2.6 OcuNotification (OcuChannel)

User callback function NOTE: please use NULL or NULL_PTR w/o any quotes. If the used string is different from NULL or NULL_PTR it will be used as the configured function name.

Table 4-22. Attribute OcuNotification (OcuChannel) detailed description

Property	Value
Type	FUNCTION-NAME
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	NULL_PTR

4.5.2.7 OcuOuptutPinUsed (OcuChannel)

Information about the usage of an output pin on this channel.

Table 4-23. Attribute OcuOuptutPinUsed (OcuChannel) detailed description

Property	Value
Type	BOOLEAN
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	false

4.5.2.8 OcuOutputPinDefaultState (OcuChannel)

The parameter OcuOutputPinDefaultState represents the state that a pin associated with a channel shall be set to after initialisation.

Table 4-24. Attribute OcuOutputPinDefaultState (OcuChannel) detailed description

Property	Value
Type	ENUMERATION
Origin	AUTOSAR_ECUC
Symbolic Name	false
Default	OCU_LOW
Enable	false
Range	OCU_HIGH OCU_LOW

4.5.2.9 OcuOutputPinAction (OcuChannel)

The parameter OcuOutputPinAction represents the action that a pin associated with a channel shall be set immediately after a compare match event.

Table 4-25. Attribute OcuOutputPinAction (OcuChannel) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Default	OCU_DISABLE
Enable	false
Range	OCU_SET_LOW OCU_SET_HIGH OCU_TOGGLE OCU_DISABLE

4.5.2.10 OcuUseMcuReferencePoint (OcuChannel)

This parameter allows for automatic calculation of the Channel Tick duration based on the configured MCU Referenced Clock. If OcuUseMcuReferencePoint is set to true than selectig a Clock source from MCU is possible and based on that source clock OcuChannelTickDuration can be auto-calculated.

Table 4-26. Attribute OcuUseMcuReferencePoint (OcuChannel) detailed description

Property	Value
Type	BOOLEAN
Origin	Custom
Symbolic Name	false
Default	false

4.5.2.11 OcuChannelTickDuration (OcuChannel)

Specifies the tick duration of the counter of the channel. This parameter is the number of the input clock edges (rising edges or falling edges exclusively) counted each time to increase the counter by one unit. Note. The default value is calculated using a default prescaler of 1. For a different prescaler value the calculated value should be divided by the said prescaler value.

Table 4-27. Attribute OcuChannelTickDuration (OcuChannel) detailed description

Property	Value
Type	INTEGER
Origin	AUTOSAR_ECUC
Symbolic Name	false
Invalid	XPath Range ≤ 65535 ≥ 0

4.5.2.12 OcuMcuClockReferencePoint (OcuChannel)

Reference to the Ftm clock source configuration, which will be configured from the MCU driver, the McuClockReferencePoint container, in McuClockSettingConfig. Selecting the desired Clock source from MCU is selectable by the Ocu Clock Source from the OcuHwSpecificSettings. For example, for OCU_EXTERNAL_CLOCK configured in Ocu Clock Source, only FLEXTIMER0_EXT_CLK may be selected as a clock source from MCU. For more information please see the Ftm subchapter from the Clocking chapter in the RM.

Table 4-28. Attribute OcuMcuClockReferencePoint (OcuChannel) detailed description


Property	Value
Type	REFERENCE
Origin	Custom

4.5.3 Form OcuHWSpecificSettings

This container contains Ocu-specific parameters for selecting the clock source and setting optional prescalers if supported by hardware.



Is included by form : [Form OcuConfigSet](#)


OcuHWSpecificSettings



Name  OcuHWSpecificSettings_0


General


FTM Module

 FTM_1 


 OcuClockSource*

 OCU_SYSTEM_CLOCK 

 OcuPrescale

 DIV1

OcuPrescale_Alternate

 DIV1

Debug Mode



 CNT_ON_OUTPUTS_ON 

Figure 4-7. Tresos Plugin snapshot for OcuHWSpecificSettings form.

4.5.3.1 OcuHardwareChannelId (OcuHWSpecificSettings)

Channel ID of the OCU hardware channel. This ID is used to match with OcuChannel/ OcuAssignedHardwareChannel

4.5.3.2 OcuFtmModule (OcuHWSpecificSettings)

Selects one Ftm modules available on the platform.

Table 4-29. Attribute OcuFtmModule (OcuHWSpecificSettings) detailed description

Property	Value
Type	STRING
Origin	NXP

Table continues on the next page...

Table 4-29. Attribute OcuFtmModule (OcuHWSpecificSettings) detailed description (continued)

Property	Value
Symbolic Name	false
Range	FTM_0, FTM_1, FTM_2, FTM_3, FTM_4, FTM_5, FTM_6, FTM_7

4.5.3.3 OcuClockSource (OcuHWSpecificSettings)

The OCU driver specific clock input for the unit can statically be configured to select different clock sources if provided by hardware. Enumeration literals are defined vendor specific.

Table 4-30. Attribute OcuClockSource (OcuHWSpecificSettings) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Optional	true
Range	OCU_SYSTEM_CLOCK, OCU_EXTERNAL_CLOCK

4.5.3.4 OcuPrescale (OcuHWSpecificSettings)

Specifies the default threshold for the channel after Ocu_StartChannel.

Table 4-31. Attribute OcuPrescale (OcuHWSpecificSettings) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Optional	true
Range	DIV1 DIV2 DIV4 DIV8 DIV16 DIV32 DIV64 DIV128

4.5.3.5 OcuPrescale_Alternate (OcuHWSpecificSettings)

Select input count source (clock) used for this eTimer channel. This parameter will be used by the Ocu_SetClockMode function.

Table 4-32. Attribute OcuPrescale_Alternate (OcuHWSpecificSettings) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Optional	true
Range	DIV1 DIV2 DIV4 DIV8 DIV16 DIV32 DIV64 DIV128

4.5.3.6 OcuPrescale_Alternate (OcuHWSpecificSettings)

Select input count source (clock) used for this FTM module. This parameter will be used by the Ocu_SetClockMode function.

Table 4-33. Attribute OcuPrescale_Alternate (OcuHWSpecificSettings) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Range	DIV1 DIV2 DIV4 DIV8 DIV16 DIV32 DIV64 DIV128

4.5.3.7 OcuDebugMode (OcuHWSpecificSettings)

OcuDebugMode These bits allow select the behavior of the FTM counter, the CH(n)F bit, the channels output, and the writing to the MOD, CNTIN, and C(n)V registers (wave form register)

CNT_ON_OUTPUTS_ON - Continue with normal operation during debug mode.

CNT_STOPED_OUTPUTS_FROZEN - Counter is stopped, channels outputs are frozen, writes to wave form registers bypass the registers buffers

CNT_STOPED_OUTPUTS_SAFE - Counter is stopped, channels outputs are forced to their safe value according to POLn bit, writes to wave form registers bypass the registers buffers

CNT_STOPED_FLAG_SET - Counter is stopped, channels outputs operate with its functionality, writes to wave form registers bypass the registers buffers

Table 4-34. Attribute OcuDebugMode (OcuHWSpecificSettings) detailed description

Property	Value
Type	ENUMERATION
Origin	Custom
Symbolic Name	false
Range	CNT_ON_OUTPUTS_ON, CNT_STOPED_OUTPUTS_FROZEN, CNT_STOPED_OUTPUTS_SAFE, CNT_STOPED_FLAG_SET

4.6 Form CommonPublishedInformation

Common container, aggregated by all modules. It contains published information about vendor and versions.




Figure 4-8. Tressos Plugin snapshot for CommonPublishedInformation form.

4.6.1 ArReleaseMajorVersion (CommonPublishedInformation)

Major version number of AUTOSAR specification on which the appropriate implementation is based on.

Table 4-35. Attribute ArReleaseMajorVersion (CommonPublishedInformation) detailed description

Property	Value
Label	AUTOSAR Major Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	4
Invalid	Range <div> <div>>=4</div> <div><=4</div> </div>

4.6.2 ArReleaseMinorVersion (CommonPublishedInformation)

Minor version number of AUTOSAR specification on which the appropriate implementation is based on.

Table 4-36. Attribute ArReleaseMinorVersion (CommonPublishedInformation) detailed description

Property	Value
Label	AUTOSAR Minor Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	3
Invalid	Range <div> <div>>=3</div> <div><=3</div> </div>

4.6.3 ArReleaseRevisionVersion (CommonPublishedInformation)

Revision version number of AUTOSAR specification on which the appropriate implementation is based on.

Table 4-37. Attribute ArReleaseRevisionVersion (CommonPublishedInformation) detailed description

Property	Value
Label	AUTOSAR Release Revision Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	1
Invalid	Range >=1 <=1

4.6.4 ModuleId (CommonPublishedInformation)

Module ID of this module from Module List.

Table 4-38. Attribute ModuleId (CommonPublishedInformation) detailed description

Property	Value
Label	Module Id
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	125
Invalid	Range >=125 <=125

4.6.5 SwMajorVersion (CommonPublishedInformation)

Major version number of the vendor specific implementation of the module. The numbering is vendor specific.

Table 4-39. Attribute SwMajorVersion (CommonPublishedInformation) detailed description

Property	Value
Label	Software Major Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false

Table continues on the next page...

Table 4-39. Attribute SwMajorVersion (CommonPublishedInformation) detailed description (continued)

Property	Value
Default	1
Invalid	Range >=1 <=1

4.6.6 SwMinorVersion (CommonPublishedInformation)

Minor version number of the vendor specific implementation of the module. The numbering is vendor specific.

Table 4-40. Attribute SwMinorVersion (CommonPublishedInformation) detailed description

Property	Value
Label	Software Minor Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	0
Invalid	Range >=0 <=0

4.6.7 SwPatchVersion (CommonPublishedInformation)

Patch level version number of the vendor specific implementation of the module. The numbering is vendor specific.

Table 4-41. Attribute SwPatchVersion (CommonPublishedInformation) detailed description

Property	Value
Label	Software Patch Version
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	1
Invalid	Range >=1 <=1

4.6.8 VendorApiInfix (CommonPublishedInformation)

In driver modules which can be instantiated several times on a single ECU, BSW00347 requires that the name of APIs is extended by the VendorId and a vendor specific name. This parameter is used to specify the vendor specific name. In total, the implementation specific name is generated as follows:

<ModuleName>_<VendorId>_<VendorApiInfix><Api name from SWS>. E.g. assuming that the VendorId of the implementor is 123 and the implementer chose a VendorApiInfix of "v11r456" a api name Can_Write defined in the SWS will translate to Can_123_v11r456Write. This parameter is mandatory for all modules with upper multiplicity > 1. It shall not be used for modules with upper multiplicity =1.

Table 4-42. Attribute VendorApiInfix (CommonPublishedInformation) detailed description

Property	Value
Label	Vendor Api Infix
Type	STRING_LABEL
Origin	Custom
Symbolic Name	false
Default	
Enable	false

4.6.9 VendorId (CommonPublishedInformation)

Vendor ID of the dedicated implementation of this module according to the AUTOSAR vendor list.

Table 4-43. Attribute VendorId (CommonPublishedInformation) detailed description

Property	Value
Label	Vendor Id
Type	INTEGER_LABEL
Origin	Custom
Symbolic Name	false
Default	43
Invalid	Range >=43 <=43

How to Reach Us:**Home Page:**nxp.com**Web Support:**nxp.com/support

Information in this document is provided solely to enable system and software implementers to use NXP products. There are no express or implied copyright licenses granted hereunder to design or fabricate any integrated circuits based on the information in this document. NXP reserves the right to make changes without further notice to any products herein.

NXP makes no warranty, representation, or guarantee regarding the suitability of its products for any particular purpose, nor does NXP assume any liability arising out of the application or use of any product or circuit, and specifically disclaims any and all liability, including without limitation consequential or incidental damages. "Typical" parameters that may be provided in NXP data sheets and/or specifications can and do vary in different applications, and actual performance may vary over time. All operating parameters, including "typicals," must be validated for each customer application by customer's technical experts. NXP does not convey any license under its patent rights nor the rights of others. NXP sells products pursuant to standard terms and conditions of sale, which can be found at the following address: nxp.com/SalesTermsandConditions.

While NXP has implemented advanced security features, all products may be subject to unidentified vulnerabilities. Customers are responsible for the design and operation of their applications and products to reduce the effect of these vulnerabilities on customer's applications and products, and NXP accepts no liability for any vulnerability that is discovered. Customers should implement appropriate design and operating safeguards to minimize the risks associated with their applications and products.

NXP, the NXP logo, NXP SECURE CONNECTIONS FOR A SMARTER WORLD, COOLFLUX, EMBRACE, GREENCHIP, HITAG, I2C BUS, ICODE, JCOP, LIFE VIBES, MIFARE, MIFARE CLASSIC, MIFARE DESFire, MIFARE PLUS, MIFARE FLEX, MANTIS, MIFARE ULTRALIGHT, MIFARE4MOBILE, MIGLO, NTAG, ROADLINK, SMARTLX, SMARTMX, STARPLUG, TOPFET, TRENCHMOS, UCODE, Freescale, the Freescale logo, AltiVec, C-5, CodeTEST, CodeWarrior, ColdFire, ColdFire+, C-Ware, the Energy Efficient Solutions logo, Kinetis, Layerscape, MagniV, mobileGT, PEG, PowerQUICC, Processor Expert, QorIQ, QorIQ Qonverge, Ready Play, SafeAssure, the SafeAssure logo, StarCore, Symphony, VortiQa, Vybrid, Airfast, BeeKit, BeeStack, CoreNet, Flexis, MXC, Platform in a Package, QUICC Engine, SMARTMOS, Tower, TurboLink, and UMEMS are trademarks of NXP B.V. All other product or service names are the property of their respective owners. AMBA, Arm, Arm7, Arm7TDMI, Arm9, Arm11, Artisan, big.LITTLE, Cordio, CoreLink, CoreSight, Cortex, DesignStart, DynamIQ, Jazelle, Keil, Mali, Mbed, Mbed Enabled, NEON, POP, RealView, SecurCore, Socrates, Thumb, TrustZone, ULINK, ULINK2, ULINK-ME, ULINK-PLUS, ULINKpro, μ Vision, Versatile are trademarks or registered trademarks of Arm Limited (or its subsidiaries) in the US and/or elsewhere. The related technology may be protected by any or all of patents, copyrights, designs and trade secrets. All rights reserved. Oracle and Java are registered trademarks of Oracle and/or its affiliates. The Power Architecture and Power.org word marks and the Power and Power.org logos and related marks are trademarks and service marks licensed by Power.org.

© 2019 NXP B.V.

Document Number UM20CUASR4.3 Rev0001R1.0.1
Revision 1.0